EuroScope ATC Client

Installation guides, modification and troubleshooting

- [Introduction](#)
- [Installation](#)
- [Updating sectorfiles](#)

Introduction

VATSCA has in collaboration with AeroNav made the sector files, plugins, and other files available via GNG, this means:

- Sectorfiles are now automatically updated
- AIRAC data is automatically updated
- Sectorfiles are downloaded from Euroscope Directly

This guide will take you through installing and updating the GNG files. ***Please read it carefully!***

We always recommend running the latest version of Euroscope for the best compatibility.

Installation

Table of Contents

Prerequisites

Before installing EuroScope be sure to download and install the latest C++ redistributable package from Microsoft. They can be downloaded from here

Also, download and install a modified version of the Euroscope font from here

Installation (Text)

Installation of EuroScope is straightforward. Just follow the instructions of the installer. Well, you should only specify the folder you would like to put the files.

Press Next to get to the location selector screen:

Select the appropriate folder where you would like to place EuroScope. Then press Next again to see the final confirmation screen:

Sectorfiles

Start Euroscope and cancel the sector selector In Euroscope click «Open SCT» at the top and select «Download Sector Files»

On the first installation, you will only have "EuroScope main sectorfile provider" Select it and click download, this gives us all the Sectorfile providers.

Now find "AeroNav GNG Sector File Provider" select it, click download, and check the automatic update box

Once downloaded, you will have 50+ sectorfile locations to pick from, find "AeroNav GNG SCA VATSIM Scandinavia" select it, and click download, remember to check the auto-update box

Now at the bottom of the window, you can find the "EKDK EKDK FIR-Full-Package" Download it, DO NOT click the automatic here as this is only for the first-time installation.

Once downloaded click the "EKDK EKDK FIR-Update-Only" download it, and click the automatic here as this is what updates your sector files

Now close EuroScope, cancel any popups and start EuroScope again. Now you should see the DK AIR and DK GND sectorfiles, for <S2 select GND.

Installation (Video)

IMAGE ALT TEXT HERE

Updating sectorfiles

If you installed EuroScope following our guide, files should automatically download.

Sectorfiles will update

- Approx. Every 28 days when new AIRAC comes
- When a major change is published within our internal files

Please be advised: Sometimes it can take 1-2 minutes before the prompt for updates appears. It can sometimes be slow

What to look for

When an update is published you will automatically be alerted via Euroscope by a total of **Three** messages.

1. A new Sectorfile is available, do you want to **download** --> Click **Yes**

2. Do you want to **use** the downloaded sectorfile --> Click **Yes**

3. If you want Euroscope to **delete** old sectorfile --> Click **Yes**

EuroScope ✕

❓ Shall I delete the old
C:\Users\Jukas\Documents\EuroScope\EKDK-EKDK-Copenhage
n_20210704124155-210601-0001.sct sector file?

Yes   No